

New parameterization of effective nucleon-nucleon t -matrix interaction for scattering at intermediate energies.

N.B.Ladygina

E-mail:nladygina@jinr.ru

Abstract

The model suggested by Love and Franey for description of the nucleon-nucleon interaction was used as the base. The new fitting of the model parameters was done in the energy range from 100 MeV up to 1100 MeV. It is based on the modern partial-wave-analysis solution for NN-amplitudes. The three observables: differential cross section, vector analyzing power, and spin correlation coefficient – were obtained at every energy. The results are compared with existing the experimental data.

In order to solve the problems of the nucleon-nucleus scattering, it is very important to know the coupling between two nucleons. A quantitative knowledge of the nucleon-nucleon coupling from first principles over a wide energy range must await a more complete theory of strong interaction.

In this connection it is useful to have a model which describe the effective nucleon-nucleon interaction. Such phenomenological model was suggested by W.G.Love and M.A.Franey in ref.[1]. According to this paper t -matrix can be expressed in the following form

$$\begin{aligned} t^{sym}(E^*, \Theta^*) &= A'(E^*, \Theta^*)P_S + B'(E^*, \Theta^*)P_T + C'(E^*, \Theta^*)((\vec{\sigma}_1 + \vec{\sigma}_2) \cdot \hat{n}) + \\ &+ E'(E^*, \Theta^*)S_{12}(\hat{q}) + F'(E^*, \Theta^*)S_{12}(\hat{Q}), \end{aligned} \quad (1)$$

where E^* is the center-of-mass energy; Θ^* is the scattering angle in the c.m. system. The unit vectors $\hat{q}, \hat{Q}, \hat{n}$ form a right-handed coordinate system with

$$\hat{q} = \frac{\vec{k} - \vec{k}'}{|\vec{k} - \vec{k}'|}, \quad \hat{Q} = \frac{\vec{k} + \vec{k}'}{|\vec{k} + \vec{k}'|}, \quad \hat{n} = \hat{q} \times \hat{Q}, \quad (2)$$

where $\vec{k}$ and $\vec{k}'$ are the initial and final momenta in the c.m. system.

The usual tensor operator $S_{12}(\hat{k}) = 3(\vec{\sigma}_1 \hat{k})(\vec{\sigma}_2 \hat{k}) - (\vec{\sigma}_1 \vec{\sigma}_2)$, the singlet spin-projection operator $P_S = \frac{1}{4}(1 - (\vec{\sigma}_1 \vec{\sigma}_2))$, and the triplet spin-projection operator $P_T = \frac{1}{4}(3 + (\vec{\sigma}_1 \vec{\sigma}_2))$ were used in Eq.(1). It should be noted, that t -matrix, here, is the antisymmetrized one, i.e. $t^{sym} = [1 - P_{12}]t$, where P_{12} is the permutation operator of the particles of "1" and "2".

This t -matrix is connected with NN -amplitude M by the relationship

$$t_{NN}(E^*, \theta^*) = -\frac{4\pi}{E^*}M(E^*, \theta^*). \quad (3)$$

The amplitudes A', B', C', E', F' are parameterized according to the symmetric properties. In case, when isospin NN -pare equals to zero, $I = 0$, these amplitudes have the following form

$$\begin{aligned} A'_0 &= \frac{4\pi R_i^3}{(2\pi)^3} V_i^{SO} \left(\frac{1}{1 + q^2 R_i^2} - \frac{1}{1 + Q^2 R_i^2} \right) \\ B'_0 &= \frac{4\pi R_i^3}{(2\pi)^3} V_i^{TE} \left(\frac{1}{1 + q^2 R_i^2} + \frac{1}{1 + Q^2 R_i^2} \right) \\ C'_0 &= \frac{2\pi i R_i^5}{(2\pi)^3} V_i^{LSE} qQ \left(\frac{1}{(1 + q^2 R_i^2)^2} - \frac{1}{(1 + Q^2 R_i^2)^2} \right) \\ E'_0 &= -\frac{32\pi i R_i^7}{(2\pi)^3} V_i^{TNE} \frac{q^2}{(1 + q^2 R_i^2)^3} \\ F'_0 &= -\frac{32\pi i R_i^7}{(2\pi)^3} V_i^{TNE} \frac{Q^2}{(1 + Q^2 R_i^2)^3}. \end{aligned} \quad (4)$$

For $I = 1$ these amplitudes are

$$\begin{aligned}
A'_1 &= \frac{4\pi R_i^3}{(2\pi)^3} V_i^{SE} \left(\frac{1}{1+q^2 R_i^2} + \frac{1}{1+Q^2 R_i^2} \right) \\
B'_1 &= \frac{4\pi R_i^3}{(2\pi)^3} V_i^{TO} \left(\frac{1}{1+q^2 R_i^2} - \frac{1}{1+Q^2 R_i^2} \right) \\
C'_1 &= \frac{2\pi i R_i^5}{(2\pi)^3} V_i^{LSO} qQ \left(\frac{1}{(1+q^2 R_i^2)^2} + \frac{1}{(1+Q^2 R_i^2)^2} \right) \\
E'_1 &= -\frac{32\pi i R_i^7}{(2\pi)^3} V_i^{TNO} \frac{q^2}{(1+q^2 R_i^2)^3} \\
F'_1 &= \frac{32\pi i R_i^7}{(2\pi)^3} V_i^{TNO} \frac{Q^2}{(1+Q^2 R_i^2)^3}.
\end{aligned} \tag{5}$$

In this paper the new set of the coefficients R_i and V_i were obtained by fitting SP07 [2] NN amplitudes. The energy region from 100 MeV up to 1100 MeV was considered. In order to get the amplitudes subset for isospin equal to zero, the "NP" and "NP1" subsets were used. The new sets of parameters are presented in the tables below. The three observables: differential cross section, vector analyzing power and spin correlation coefficient – were obtained for every energy and were compared with the experimental data [2]. On the figures below the fitting results are presented by the red lines. The black curves correspond to the results obtained with the amplitudes from SAID [2].

The NN t -matrix can be also expressed in the standard form

$$\begin{aligned}
t(E^*, \Theta^*) &= A(E^*, \Theta^*) + B(E^*, \Theta^*)(\vec{\sigma}_1 \hat{n})(\vec{\sigma}_2 \hat{n}) + C(E^*, \Theta^*)((\vec{\sigma}_1 + \vec{\sigma}_2) \cdot \hat{n}) + \\
&+ E(E^*, \Theta^*)(\vec{\sigma}_1 \hat{q})(\vec{\sigma}_2 \hat{q}) + F(E^*, \Theta^*)(\vec{\sigma}_1 \hat{Q})(\vec{\sigma}_2 \hat{Q}).
\end{aligned} \tag{6}$$

The relationships between amplitudes A' , B' , C' , E' , F' and A , B , C , E , F can be got with comparison of the two definitions of t -matrix, Eq.(1) and Eq.(6).

$$\begin{aligned}
A &= \frac{1}{4}(A' + 3B') \\
B &= \frac{1}{4}(B' - A') - (E' + F') \\
C &= C' \\
E &= \frac{1}{4}(B' - A') + 2E' - F' \\
F &= \frac{1}{4}(B' - A') - E' + 2F'.
\end{aligned} \tag{7}$$

All notations used in this paper are the same as in ref.[1].

The work has been supported in part by the Russian Foundation for Basic Research under grant 07-02-00102a.

References

- [1] W.G.Love, M.A.Franey, Phys. Rev.C **24**, 1073 (1981); W.G.Love, M.A.Franey, Phys.Rev.C **31**, 488 (1985).
- [2] <http://gwdac.phys.gwu.edu>

$T_{lab} = 100MeV$, Re part

R	VSE	VTO	VLSE	VTNO
0.11	8352.18	4669.53	0	-600000
0.15	-680.002	-2523.94	0	23340.9
0.25	383.456	142.706	0	-200
0.4	-753.348	-895.424	0	288.248
0.55	220.39	360.761	0	-47.7974
0.7	-50.1382	-91.3391	0	5.97377
1.4	-0.966063	0.55162	0	-0.00201629

$T_{lab} = 100MeV$, Im part

R	VSE	VTO	VLSE	VTNO
0.11	-6519.78	-6037.04	17149.7	-1.17288e+06
0.15	7112.78	2053.56	-39.1544	857602
0.25	-7831.77	-5679.67	228.483	-55084.2
0.4	1901.84	962.641	1076.17	2887.14
0.55	-1.10827	21.4285	-79.9082	-310.513
0.7	62.9981	33.4869	2.20799	10.0006
1.4	9.77397	-3.48397	-0.173829	-0.0710843




$T_{lab} = 100MeV$, Re part

R	VSO	VTE	VLSE	VTNE
0.11	29001.4	-3280.68	0	1.27875e+06
0.15	-78611.4	43315.1	0	-20000
0.25	2329.43	-4559.44	0	920
0.4	-9198.27	704.897	0	-800
0.55	4694.37	-1299.19	0	145.923
0.7	-936.359	64.2434	0	-38.7549
1.4	14.9161	-6.81892	0	-0.026915




$T_{lab} = 100MeV$, Im part

R	VSO	VTE	VLSE	VTNE
0.11	-2103.44	56000	-40003.8	-400000
0.15	220004	-2500	4999.68	400
0.25	-15781.1	450	-50.032	-30000
0.4	800.06	-3476.29	1370.94	4251.08
0.55	-2027.65	1400	-80.0005	-514.627
0.7	680	-220	11.1557	92.3779
1.4	-40.7887	2.67444	-0.65136	0.140121

$$T_{lab} = 100 MeV, pp$$



$$T_{lab} = 100 MeV, np$$



$T_{lab} = 200MeV$, Re part

R	VSE	VTO	VLSE	VTNO
0.11	21605.3	5564.15	0	-1e+06
0.15	-1247.82	-5599.74	0	124038
0.25	333.265	149.951	0	-800
0.4	-1299.38	-908.962	0	153.371
0.55	434.175	359.347	0	-35.7073
0.7	-91.1403	-82.007	0	5.46177
1.4	0.00100003	0.498954	0	-0.00872548

$T_{lab} = 200MeV$, Im part

R	VSE	VTO	VLSE	VTNO
0.11	-8624.53	-8271.96	18202.5	-816552
0.15	7230.76	5172.77	-87.9493	300032
0.25	-8081.44	-6332.04	230.637	-20160.7
0.4	2166.57	1008.42	1149.09	1677.25
0.55	-164.434	24.2187	-151.771	-290.396
0.7	131.628	20.3244	7.41174	19.102
1.4	7.79064	-3.39373	0.0362834	-0.111059




$T_{lab} = 200MeV$, Re part

R	VSO	VTE	VLSE	VTNE
0.11	25999.9	-5359.08	0	850000
0.15	-41962.5	27454.7	0	-40000
0.25	2185.95	-3999.81	0	972.163
0.4	-5768.09	700.001	0	-800
0.55	3625.01	-799.977	0	117.309
0.7	-950	37.101	0	-26.6337
1.4	23.5844	-7.1173	0	-0.0774762




$T_{lab} = 200MeV$, Im part

R	VSO	VTE	VLSE	VTNE
0.11	-4000.02	35929.1	-60000.4	-200000
0.15	249994	-4938.93	2999.99	76436.7
0.25	-20027.1	280.001	-100.002	-16000
0.4	1226.74	-2999.9	1099.95	2810.16
0.55	-2389.81	1370.36	-159.609	-351.581
0.7	704.295	-150	22.2239	68
1.4	-33.4615	2.34164	-0.450722	0.320879

$$T_{lab} = 200 \text{ MeV, pp}$$



$$T_{lab} = 200 MeV, np$$



$T_{lab} = 300MeV$, Re part

R	VSE	VTO	VLSE	VTNO
0.11	26672.7	6019.47	0	-1.18252e+06
0.15	-440.936	-7940.31	0	209184
0.25	338.321	462.706	0	-4417.48
0.4	-1955.99	-910.192	0	330.769
0.55	662.155	357.713	0	-64.9937
0.7	-124.504	-81.137	0	10.3199
1.4	-0.211034	0.654291	0	-0.0221523

$T_{lab} = 300MeV$, Im part

R	VSE	VTO	VLSE	VTNO
0.11	-8700.55	-8520.21	30105	-315784
0.15	8994.24	6830.08	-559.126	95000
0.25	-8691.5	-6492.94	259.858	-7914.95
0.4	2398.75	1018.76	963.971	972.465
0.55	-248.855	49.6393	-151.998	-229.982
0.7	132.005	-2.2	12.2475	17.9979
1.4	7.21693	-3.03145	0.0281493	-0.13225




$T_{lab} = 300MeV$, Re part

R	VSO	VTE	VLSE	VTNE
0.11	15872.8	-9959.96	0	700000
0.15	-41011.9	16785.5	0	-74674.8
0.25	1519.37	-2500.03	0	1000
0.4	-3005.64	699.998	0	-581.599
0.55	2834.9	-498.014	0	95.6785
0.7	-976.34	20.0001	0	-25.4931
1.4	27.6585	-9.56093	0	-0.0611397




$T_{lab} = 300MeV$, Im part

R	VSO	VTE	VLSE	VTNE
0.11	-6059.03	25992.6	-83997.3	-100000
0.15	199774	-5155.48	2001.06	115271
0.25	-21601.1	400.025	-200.298	-14500
0.4	1505.84	-2299.71	1177.83	2146.74
0.55	-2451.54	1098.88	-248.234	-220
0.7	829.524	-155.576	39.9428	53.6106
1.4	-36.9757	2.83388	-0.474437	0.276692

$$T_{lab} = 300 MeV, pp$$



$$T_{lab} = 300 \text{ MeV, np}$$



$T_{lab} = 400MeV$, Re part

R	VSE	VTO	VLSO	VTNO
0.11	35128.7	8969.36	0	-1.4e+06
0.15	-573.388	-7987.51	0	305229
0.25	343.641	823.923	0	-9317.37
0.4	-2767.96	-915.473	0	529.21
0.55	929.159	300.001	0	-65.1609
0.7	-164.348	-65.5461	0	7.57547
1.4	-0.657018	0.697277	0	0.00274612

$T_{lab} = 400MeV$, Im part

R	VSE	VTO	VLSO	VTNO
0.11	-14196.8	-9755.82	34347	-174487
0.15	30704.2	7612.04	-1027.46	30005.5
0.25	-16339.6	-6599.66	259.974	-3000.55
0.4	3549.85	1022.54	839.925	599.838
0.55	-428.424	49.9533	-152	-178.924
0.7	144.327	-4.00007	16.5247	14.6032
1.4	6.439	-3.02676	-0.00171169	-0.138766




$T_{lab} = 400MeV$, Re part

R	VSO	VTE	VLSE	VTNE
0.11	10003.5	-6500.01	0	700000
0.15	-37996.9	19984.3	0	-105666
0.25	3011.6	-4313.26	0	2500
0.4	-1899.16	509.9	0	-605.942
0.55	1997.57	-400.106	0	101.344
0.7	-786.388	66.1521	0	-26.8545
1.4	27.8255	-8.85684	0	-0.0519602




$T_{lab} = 400MeV$, Im part

R	VSO	VTE	VLSE	VTNE
0.11	-9000.74	26096.1	-86161.3	-140000
0.15	150000	-6880.2	3602.31	147643
0.25	-20695.4	800.026	-500.093	-14459.2
0.4	2202.03	-2394.61	1199.98	1878.77
0.55	-2500.01	1161.22	-267.554	-180
0.7	850.16	-199.975	40.3628	52.5685
1.4	-38.5451	2.80001	-0.392178	0.178394

$$T_{lab} = 400 MeV, pp$$



$$T_{lab} = 400 MeV, np$$



$T_{lab} = 500MeV$, Re part

R	VSE	VTO	VLSO	VTNO
0.11	37862.8	14504.7	0	-1.74716e+06
0.15	-4954.58	-837.824	0	455147
0.25	3767.37	1500.01	0	-19986.4
0.4	-4346.01	-1839.63	0	1541.32
0.55	1293.77	637.077	0	-251.049
0.7	-208.814	-134.014	0	31.7401
1.4	-0.995248	1.26681	0	-0.0407424

$T_{lab} = 500MeV$, Im part

R	VSE	VTO	VLSO	VTNO
0.11	-14492.5	-20517.6	60377	-194388
0.15	89149.1	9483.94	-8021.8	16807.9
0.25	-43841.8	-6649.3	260.464	-800
0.4	9572.99	1074.55	758.391	424.257
0.55	-1771.73	49.9999	-152.473	-150.147
0.7	294.519	-6.0001	19.8721	12.6668
1.4	6.39985	-3.09034	-0.0364889	-0.142317




$T_{lab} = 500MeV$, Re part

R	VSO	VTE	VLSE	VTNE
0.11	33722.8	-12212.7	0	750000
0.15	-43521.8	23397.1	0	-161042
0.25	4500.25	-5499.99	0	7500
0.4	-1350.43	1000.49	0	-1068.63
0.55	1098.49	-664.344	0	179.948
0.7	-449.229	150	0	-36.1737
1.4	23.9514	-6.09722	0	-0.0409734




$T_{lab} = 500MeV$, Im part

R	VSO	VTE	VLSE	VTNE
0.11	-15019.4	29775.1	-93983.5	-220000
0.15	99907.1	-10333	8001.18	152897
0.25	-16195.6	1528.95	-728.691	-14042.5
0.4	3005.14	-2544.99	1246.66	1927.52
0.55	-2900.47	1099.96	-321.017	-200
0.7	946.45	-170.001	52.1427	51.7188
1.4	-40.3178	2.75396	-0.413609	0.191684

$$T_{lab} = 500 \text{ MeV}, \text{ pp}$$



$$T_{lab} = 500 \text{ MeV, np}$$



$T_{lab} = 600MeV$, Re part

R	VSE	VTO	VLSO	VTNO
0.11	39223.1	39999.2	0	-1.9818e+06
0.15	-16823.7	-859.535	0	594371
0.25	8156.47	3249.9	0	-32689.4
0.4	-4906.45	-3297.6	0	2833.79
0.55	1302.73	1137.8	0	-501.582
0.7	-214.687	-233.693	0	65.2895
1.4	-1.00004	2.0221	0	-0.108178

$T_{lab} = 600MeV$, Im part

R	VSE	VTO	VLSO	VTNO
0.11	-22964.1	-26608.4	71451	-489266
0.15	116414	25000.2	-15177.1	85000
0.25	-53112.9	-9611.59	861.466	-1897.11
0.4	10672.9	1353.9	609.355	318.405
0.55	-1961.67	50.3023	-127.863	-97.8803
0.7	300.803	-17.8269	17.5571	4.03453
1.4	6.39	-2.90834	-0.0387547	-0.113632




$T_{lab} = 600MeV$, Re part

R	VSO	VTE	VLSE	VTNE
0.11	34999.8	-23999.8	0	762619
0.15	-46778.3	25015	0	-197296
0.25	8064.22	-5701.42	0	11698
0.4	-2764.45	1834.76	0	-1422.61
0.55	1191.14	-965.507	0	220
0.7	-256.618	180.001	0	-37.7607
1.4	10.4361	-3.30028	0	-0.0672715




$T_{lab} = 600MeV$, Im part

R	VSO	VTE	VLSE	VTNE
0.11	-30002.5	35000.3	-95999.2	-350000
0.15	84998.8	-15973.9	11000	191095
0.25	-15228.7	3114.64	-971.086	-16483.9
0.4	3300.84	-3000	1295.6	2200
0.55	-2866.78	1170.99	-379.887	-260.55
0.7	907.596	-170.001	67.0043	57.0783
1.4	-39.6339	2.5781	-0.479642	0.180795

$$T_{lab} = 600 \text{ MeV, pp}$$



$$T_{lab} = 600 \text{ MeV, np}$$



$T_{lab} = 700MeV$, Re part

R	VSE	VTO	VLSE	VTNO
0.11	45263.7	34976.6	0	-1.80674e+06
0.15	-61485	-1082.61	0	616534
0.25	26601	8006.56	0	-40869.1
0.4	-7902.72	-5585.28	0	3907.26
0.55	1662.15	1885.61	0	-737.9
0.7	-216.65	-379.801	0	99.4035
1.4	-1.94428	3.12775	0	-0.183929

$T_{lab} = 700MeV$, Im part

R	VSE	VTO	VLSE	VTNO
0.11	-34920	-26764.2	46699.4	-656304
0.15	120864	75446.9	-18638.6	160970
0.25	-53431.5	-19034.7	2628.57	-6500
0.4	11362.7	1408.82	304.796	458.73
0.55	-2532.68	348.91	-66.2242	-89
0.7	445.215	-111.874	9.37959	1.91424
1.4	4.84994	-1.92047	-0.0220682	-0.112063




$T_{lab} = 700MeV$, Re part

R	VSO	VTE	VLSE	VTNE
0.11	38678.4	-33538.1	0	819999
0.15	-60050	26277.9	0	-241958
0.25	17152.3	-5845.67	0	17400.3
0.4	-5998.57	3101.48	0	-2300.32
0.55	1622.22	-1813.63	0	432.924
0.7	-84.9992	399.808	0	-70.4326
1.4	1.64853	-2.06173	0	0.0163029




$T_{lab} = 700MeV$, Im part

R	VSO	VTE	VLSE	VTNE
0.11	-53124.9	49726.5	-98084.6	-680000
0.15	64437.3	-31519.1	28523.1	270000
0.25	-11324.3	6008.46	-2698.22	-18737.3
0.4	3287	-3045.78	1332.24	2252.89
0.55	-2808.41	1306.58	-387.504	-286.462
0.7	857.454	-319.919	69.3883	61.7145
1.4	-37.3773	9.29109	-0.485126	0.131033

$$T_{lab} = 700 MeV, pp$$



$$T_{lab} = 700 \text{ MeV, np}$$



$T_{lab} = 800MeV$, Re part

R	VSE	VTO	VLSO	VTNO
0.11	45300.9	34887.9	0	-800000
0.15	-79869.3	-917.097	0	320054
0.25	36206.3	6224.42	0	-25343.3
0.4	-10176.9	-4412.2	0	2511.69
0.55	2127.49	1327.29	0	-497.576
0.7	-261.752	-258.907	0	70.3886
1.4	-2.43463	2.48021	0	-0.128731

$T_{lab} = 800MeV$, Im part

R	VSE	VTO	VLSO	VTNO
0.11	-56467.2	-13305.2	25165.4	-920000
0.15	99981	121165	-18003.1	291900
0.25	-36248.1	-31106.7	3546.83	-17421.9
0.4	6145.54	2806.01	119.925	1236.76
0.55	-1034.03	146.599	-25.1756	-156.989
0.7	204.387	-112.002	3.38124	2.05897
1.4	4.72574	-1.29686	-0.00598186	-0.0544541




$T_{lab} = 800MeV$, Re part

R	VSO	VTE	VLSE	VTNE
0.11	39000	-34171.7	0	808495
0.15	-99999.9	29618	0	-259064
0.25	27341.1	-7497.5	0	19949.5
0.4	-7133.84	3443.67	0	-2646.22
0.55	1700.12	-1865.03	0	516.977
0.7	-103.451	400	0	-82.5902
1.4	4.47402	-0.481941	0	0.0493507




$T_{lab} = 800MeV$, Im part

R	VSO	VTE	VLSE	VTNE
0.11	-82029.8	85585.8	-97896.2	-380000
0.15	54576.5	-46437.8	40754.2	175805
0.25	-8000.48	4000.48	-4054.97	-14975.3
0.4	3146.73	-2561.78	1336.19	2303.39
0.55	-2717.57	1632.37	-380	-398.557
0.7	799.87	-498.918	67.7489	86.4692
1.4	-35.4606	11.2218	-0.464504	0.0050183

$$T_{lab} = 800 \text{ MeV, pp}$$



$$T_{lab} = 800 MeV, np$$



$T_{lab} = 900MeV$, Re part

R	VSE	VTO	VLSE	VTNO
0.11	45401.6	14223.1	0	-280001
0.15	-74533.3	-909.33	0	139758
0.25	33478.5	4815.19	0	-13235
0.4	-9375.58	-2655	0	1360.05
0.55	1809.97	429.457	0	-305.773
0.7	-189.67	-47.8691	0	48.2382
1.4	-2.9259	0.8333	0	-0.0968045

$T_{lab} = 900MeV$, Im part

R	VSE	VTO	VLSE	VTNO
0.11	-84664.2	-9301.41	53744.1	-600000
0.15	99433	116767	-27889.2	225933
0.25	-28765	-30906	3551.32	-17130.4
0.4	4099.44	2829.68	159.308	1316.68
0.55	-600	114.117	-41.1986	-165.379
0.7	163.771	-116.036	6.12693	2.03006
1.4	3.70942	-0.897898	-0.0157595	-0.042234




$T_{lab} = 900MeV$, Re part

R	VSO	VTE	VLSE	VTNE
0.11	40555.1	-28315.4	0	683621
0.15	-108846	28844.1	0	-244909
0.25	28152.1	-6934.63	0	21046.9
0.4	-6500.3	1971.89	0	-2813.95
0.55	1500.04	-1021.26	0	561.755
0.7	-135.43	215.321	0	-88.4074
1.4	8.8632	-0.214113	0	0.0688726




$T_{lab} = 900MeV$, Im part

R	VSO	VTE	VLSE	VTNE
0.11	-93840.9	65153.1	-96000	-259059
0.15	49515.6	-36529.1	39991.4	134984
0.25	-5111.04	3922.52	-4000.1	-11979
0.4	2153.8	-2439.75	1272.95	1782.36
0.55	-2070.87	1212.83	-374.312	-273.571
0.7	583.589	-270.009	67.6282	66.716
1.4	-31.7335	2.15297	-0.456572	0.0514867

$$T_{lab} = 900 MeV, pp$$



$$T_{lab} = 900 \text{ MeV, np}$$



$T_{lab} = 1000 MeV$, Re part

R	VSE	VTO	VLSO	VTNO
0.11	60666.9	2888.67	0	-230463
0.15	-72709.5	-808.002	0	98816.7
0.25	28017.3	4547.87	0	-7827.76
0.4	-7447.1	-2165.55	0	644.909
0.55	1117.53	230.777	0	-164.754
0.7	-50.0001	-15.2833	0	29.8561
1.4	-3.56802	0.979312	0	-0.0626672

$T_{lab} = 1000 MeV$, Im part

R	VSE	VTO	VLSO	VTNO
0.11	-98711.2	-9057.76	129026	-300001
0.15	97688.4	96145.3	-54998.6	143127
0.25	-24155	-26263.4	4350.96	-14093.3
0.4	2897.23	2389.94	167.686	1192.58
0.55	-390.274	113.728	-60.9247	-156.562
0.7	163.013	-116.033	10.5639	2.00019
1.4	2.2639	-0.415819	-0.0387636	-0.0420831




$T_{lab} = 1000 MeV$, Re part

R	VSO	VTE	VLSE	VTNE
0.11	44901.6	-15179	0	605715
0.15	-70514.2	23029.8	0	-240000
0.25	14013.4	-6293.02	0	22538.7
0.4	-3749.13	1127	0	-2967.2
0.55	1270.4	-600.001	0	592.673
0.7	-199.734	137.29	0	-91.3122
1.4	4.82993	-0.142917	0	0.0768991




$T_{lab} = 1000 MeV$, Im part

R	VSO	VTE	VLSE	VTNE
0.11	-119999	64686.9	-90000	-120000
0.15	59750.4	-34026.4	23438.1	93524
0.25	-6000	2150.45	-1500	-10164.8
0.4	2797.14	-1557.28	906.58	1576.55
0.55	-2312.91	769.397	-309.155	-235.409
0.7	600	-150.109	60.0015	60.937
1.4	-30.1323	0.190335	-0.439257	0.0573121

$$T_{lab} = 1000 \text{ MeV, pp}$$



$$T_{lab} = 1000 \text{ MeV, np}$$



$T_{lab} = 1100 MeV$, Re part

R	VSE	VTO	VLSE	VTNO
0.11	69410.4	550	0	-185846
0.15	-71738.4	-808	0	72199.7
0.25	25344	4289.49	0	-4635.81
0.4	-6844.69	-1986.87	0	250
0.55	993.501	175	0	-98.0508
0.7	-36.194	-9.61922	0	22.7208
1.4	-3.27555	1.13202	0	-0.0626293

$T_{lab} = 1100 MeV$, Im part

R	VSE	VTO	VLSE	VTNO
0.11	-102796	-9017.06	181874	-120000
0.15	95875.2	81222.3	-74712.7	85623.9
0.25	-22050.9	-23137.9	4967.06	-11257.2
0.4	2184.63	2204.78	168	1058.8
0.55	-100.491	87.9625	-76.9202	-149.126
0.7	94.7553	-117.096	14.3827	2.58782
1.4	2.25999	-0.100002	-0.0596146	-0.0456317




$T_{lab} = 1100 MeV$, Re part

R	VSO	VTE	VLSE	VTNE
0.11	48439.2	-13708.4	0	551305
0.15	-59038.5	22873.1	0	-235000
0.25	7698.42	-6077.29	0	23953.4
0.4	-1908.28	650.012	0	-3143.67
0.55	1121.09	-398.936	0	631.914
0.7	-319.695	109.256	0	-95.9452
1.4	4.6774	-0.110743	0	0.0900328

$T_{lab} = 1100 MeV$, Im part

R	VSO	VTE	VLSE	VTNE
0.11	-218411	41234.9	-86000	-60000
0.15	86984	-21169.5	15583.9	69533.6
0.25	-6075.13	1340.98	-600	-8687.87
0.4	5346.6	-1196.53	818.464	1358.4
0.55	-4490.38	500.001	-300	-186.977
0.7	1269.38	-85.6839	58.3339	53.0555
1.4	-38.4122	0.104405	-0.402291	0.0701362

$$T_{lab} = 1100 \text{ MeV, pp}$$



$$T_{lab} = 1100 \text{ MeV, np}$$

