

Spin-accumulation capacitance and its application to magnetoimpedance

Yao-Hui Zhu, Xiao-Xue Zhang, Jian Liu and Pei-Song He

Physics Department, Beijing Technology and Business University, Beijing
100048, China

E-mail: yaohuizhu@gmail.com

February 2017

Abstract. In magnetic multilayers, spin accumulation manifests itself as an excess of electrons in one spin channel and an equal deficiency in the other under the quasi-neutrality condition. Here, taking a typical ferromagnet/nonmagnet (FM/NM) junction as an example, we model the two spin channels as the two plates of a capacitor. This enables us to introduce the spin-accumulation (SA) capacitance to measure the ability of a material to store spins. The energy stored in the SA capacitor corresponds to the splitting energy of the spin-dependent chemical potentials instead of the electrostatic field energy, which is similar to quantum capacitance. Spin relaxation is modeled naturally as the leakage current of the SA capacitor. The extra heat generation due to the spin relaxation and diffusion can be written formally as the Joule heating of various effective resistances, which add up to the spin-coupled interface resistance of the FM/NM junction. As an application, the SA capacitances are used to reinterpret the imaginary part (reactance) of the low-frequency magnetoimpedance, which was previously attributed to a diffusion capacitance.

Keywords: Spin-accumulation capacitance, diffusion capacitance, magnetoimpedance

Submitted to: *J. Phys. D: Appl. Phys.*

1. Introduction

It is well-known that capacitance plays an important role in vast types of electrical and electronic devices. In many applications, it has remarkable influence on the speed of the devices and also sets an upper frequency limit (cutoff frequency) for their correct operations. [1] Its effects on spintronic devices have also been observed and analyzed. The magnetocapacitance or magnetoimpedance has been studied, for example, in magnetic tunnel junctions (MTJs) [2, 3, 4, 5, 6, 7] and in a single electron transistor [8].

Using a time-dependent approach, Rashba has studied the frequency-dependent impedance of a junction composed of a ferromagnetic (FM) conductor, a spin-selective tunnel or Schottky contact, and a nonmagnetic (NM) conductor. [9] The imaginary part of the impedance was attributed to a diffusion capacitance C_{diff} , which can be

compared to that of a p-n junction. [1] However, Rashba's derivation involved the quasi-neutrality condition, which assumes that the charge accumulation is negligible in every layer. Thus it seems difficult to reconcile this condition with the charge storage that is usually associated with the diffusion capacitance. [1] In the present paper, we try to resolve this problem by introducing a *spin-accumulation* (SA) capacitance for each layer. This new type of capacitance measures the ability of a material to store spins instead of charge. In an SA capacitor, the electron accumulation happens in the spin degree of freedom instead of the coordinate space. Thus a spatial charge accumulation is not essential here. Furthermore, the diffusion capacitance C_{diff} in Rashba's work was not written in a form resembling that of a typical p-n junction. [1] Fortunately, this task can also be accomplished by using the SA capacitances, whose form is obviously similar to the diffusion capacitance. The low-frequency magnetoimpedance of the FM/NN junction can also be written in terms of the SA capacitances by using an equivalent circuit.

The form of energy storage associated with the diffusion capacitance is another basic question, because it indicates the type and origin of the capacitance. However, this issue has not been addressed to our knowledge. [1, 9] On the other hand, most studies on the magnetoimpedance of the MTJs assumed that the energy is stored in an extra electrostatic field like usual geometrical capacitances. [2, 4] Here, we will also show that the energy storage associated with the magnetoimpedance of the FM/NM junction is equal to that stored in the SA capacitors. It is the splitting energy of the spin-dependent chemical potentials instead of the electrostatic energy. This characteristic is similar to that of quantum capacitance, which stores energy in forms other than the electrostatic field. [10, 11]

This paper is organized as follows. In section 2, we introduce the SA capacitance for the FM/NM junction. Then the model is used to reinterpret the magnetoimpedance in section 3. The main conclusions are given in section 4.

2. Spin-accumulation capacitance

To illustrate the concept of the SA capacitance, we consider the well-known configuration giving rise to spin accumulation, that is, magnetic multilayers with current perpendicular to the plane. [12] To be specific, we consider the same FM/NM junction studied by Rashba. [9] The junction is composed of a ferromagnetic layer occupying $z < 0$, a spin-selective contact at $z = 0$, and a nonmagnetic layer occupying $z > 0$. The z axis is set to be perpendicular to the layer plane as shown in figure 1. Without loss of generality, the magnetization of the FM is set to be "up" and the current is flowing in the positive direction of the z axis.

Although the importance of capacitance usually shows up in time-dependent transport, it is also present in the constant DC situation, which is much easier to deal with. The spin accumulation is usually described by the splitting of the spin-dependent chemical potentials

$$\mu_m(z) = 2\Delta\mu(z) = \mu_+(z) - \mu_-(z), \quad (1)$$

where the subscripts "+" and "-" stand for the absolute spin directions "up" and "down", respectively. [12] In each layer, $\Delta\mu(z)$ obeys the well-established spin diffusion equation

$$\frac{\partial^2 \Delta\mu(z)}{\partial z^2} = \frac{\Delta\mu(z)}{l_{\text{sf}}^2}, \quad (2)$$




Figure 1. (a) Sketch of the spin-dependent charge density $\rho_{\pm}(z)$ in the FM/NM junction. The curves are plotted according to (6) but without using realistic parameters, because a demonstration of the basic profile is enough for our current purpose. The units for $\rho_{\pm}(z)$ and z are arbitrary. The constant DC current has a density of J_0 . The solid curves on the left and right sides of the interface at $z = 0$ stand for $\rho_{+}(z)$ in the FM and NM layers, respectively. Similarly, the dashed curves are for $\rho_{-}(z)$. The vertical dotted lines indicate the scale of the spin diffusion lengths, l_{sf}^F and l_{sf}^N , in the FM and NM layers, respectively. The capacitances C_{sa}^F and C_{sa}^N are defined by (10).

where l_{sf} is the spin-diffusion length (see Appendix A for details). The solution to (2) in each layer is of exponential form as shown by (A.10) and (A.11). Introducing the average chemical potential $\mu(z) = [\mu_{+}(z) + \mu_{-}(z)]/2$ and using (1), we can write the spin-dependent chemical potentials as

$$\mu_{\pm}(z) = \mu(z) \pm \Delta\mu(z). \quad (3)$$

Since we are concerned with capacitance, it is more convenient to use the charge accumulation in the two spin channels

$$\rho_{\pm}(z) = -eN_s [\mu_{\pm}(z) - \mu^0], \quad (4)$$

where $-e$ is the charge of an electron and N_s the density of states at the Fermi level μ^0 . [13, 14] According to the Valet-Fert theory, [12] N_s is assumed to be the same for the two spin directions and also for both layers. We have $\mu(z) = \mu^0$ in the NM layer, [14] where the bulk spin asymmetry coefficient β is zero. In the FM layer, $\mu(z)$ is unequal to μ^0 in general. However, it can be justified for our problem to assume

$$\mu(z) = \mu^0 \quad (5)$$

even in the FM layer according to the quasi-neutrality approximation (see Appendix B). Then substituting (3) and (5) into (4), we have

$$\rho_{\pm}(z) = \mp eN_s \Delta\mu(z), \quad (6)$$

which is valid in both FM and NM layers. Therefore, the electron excess in one spin channel cancels the deficiency in the other, $\rho_{+}(z) + \rho_{-}(z) = 0$, in both layers.

The basic idea of the SA capacitance arises initially from the resemblance of charge storage between the two spin channels and the two plates of a normal capacitor, as shown in figure 1. Further analysis shows that the spin accumulation also bears similarity to a capacitor in other aspects, including energy storage, leakage current, and heat generation.

Charge storage When the two spin channels are modeled as the two plates of the SA capacitor, the charge storage of the capacitor can be defined as the absolute value of the charge accumulation in either spin channel. Treating the FM and NM layers separately, we can write the charge storage as

$$Q_{\text{sa}}^{\text{F}} = \int_{-\infty}^0 |\rho_{\pm}(z)| dz = \int_{-\infty}^0 eN_s |\Delta\mu(z)| dz, \quad (7)$$

$$Q_{\text{sa}}^{\text{N}} = \int_0^{\infty} |\rho_{\pm}(z)| dz = \int_0^{\infty} eN_s |\Delta\mu(z)| dz, \quad (8)$$

where (6) has been used. Following the procedure detailed in Appendix A, we can write Q_{sa}^{F} and Q_{sa}^{N} in a form resembling a normal capacitor

$$Q_{\text{sa}}^{\text{F}} = C_{\text{sa}}^{\text{F}} V_{\text{c}}^{\text{F}}, \quad Q_{\text{sa}}^{\text{N}} = C_{\text{sa}}^{\text{N}} V_{\text{c}}^{\text{N}}, \quad (9)$$

where we have introduced the SA capacitances

$$C_{\text{sa}}^{\text{F}} = \frac{T_1^{\text{F}}}{2r_{\text{F}}}, \quad C_{\text{sa}}^{\text{N}} = \frac{T_1^{\text{N}}}{2r_{\text{N}}}, \quad (10)$$

and the corresponding effective potentials

$$V_{\text{c}}^{\text{F}} = \frac{|\Delta\mu(0^-)|}{e}, \quad V_{\text{c}}^{\text{N}} = \frac{|\Delta\mu(0^+)|}{e}, \quad (11)$$

for the *semi-infinite* FM and NM layers, respectively. In the expression of $C_{\text{sa}}^{\text{F(N)}}$ given in (10), T_1^{F} (T_1^{N}) is the spin relaxation time in the FM (NM) layer. [13] The resistances r_{F} and r_{N} are defined as [15]

$$r_{\text{F}} = \rho_{\text{F}}^* l_{\text{sf}}^{\text{F}}, \quad r_{\text{N}} = \rho_{\text{N}}^* l_{\text{sf}}^{\text{N}}, \quad (12)$$

where ρ_{F}^* (ρ_{N}^*) is the FM (NM) resistivity (see Appendix A). Using the expressions of $\Delta\mu(0^-)$ and $\Delta\mu(0^+)$ in (A.12), we can rewrite (11) in a form similar to Ohm's law

$$V_{\text{c}}^{\text{F}} = r_{\text{F}}^{\text{sf}} |\alpha_{\text{F}}| \frac{J_0}{2}, \quad V_{\text{c}}^{\text{N}} = r_{\text{N}}^{\text{sf}} |\alpha_{\text{N}}| \frac{J_0}{2}, \quad (13)$$

where we have defined the dimensionless parameters

$$\alpha_{\text{F}} = \frac{\beta(r_{\text{N}} + r_{\text{b}}^*) - \gamma r_{\text{b}}^*}{r_{\text{F}} + r_{\text{b}}^* + r_{\text{N}}}, \quad \alpha_{\text{N}} = \frac{\beta r_{\text{F}} + \gamma r_{\text{b}}^*}{r_{\text{F}} + r_{\text{b}}^* + r_{\text{N}}}, \quad (14)$$

and the characteristic (spin-flip) resistances

$$r_{\text{F}}^{\text{sf}} = 2r_{\text{F}}, \quad r_{\text{N}}^{\text{sf}} = 2r_{\text{N}}, \quad (15)$$

for the FM and NM layers, respectively. In (14), the interfacial resistance r_{b}^* and its spin asymmetry coefficient γ are defined in Appendix A. In general, the effective potentials V_{c}^{F} and V_{c}^{N} are not equal to each other due to the interface resistance. In the configuration specified above ("up" magnetization and positive DC current), α_{N} is always positive, whereas α_{F} may be negative. Their interpretation will be given by (21) in combination with the effective circuit shown in figure 2(b).

The expression of $C_{\text{sa}}^{\text{F(N)}}$ in (10) is similar to that of the diffusion capacitance in a p-n junction. [1] However, $C_{\text{sa}}^{\text{F(N)}}$ does not require a spatial charge imbalance, which is essential for the diffusion capacitance in a p-n junction. Therefore, $C_{\text{sa}}^{\text{F(N)}}$ measures the ability of a material to store spins instead of charge. Spin accumulating and dissipating correspond to charging and discharging of the SA capacitor, respectively. Note that $C_{\text{sa}}^{\text{F(N)}}$ cannot be compared directly with the diffusion capacitance C_{diff} in (C.5), which was introduced by Rashba. [9] One distinction between them is the independence of $C_{\text{sa}}^{\text{F(N)}}$ on the spin asymmetry coefficient β or γ .

Energy storage Since $\mu_m(z)$ is the splitting between the chemical potentials of the two spin channels, spin accumulation also accompanies an increase in energy in comparison to the equilibrium state. The energy stored in the differential dz is equivalent to the energy required to shift a number of electrons, $N_s|\Delta\mu(z)|dz$, from the spin channel with lower chemical potential to the other. Because the average energy increase per electron is just $|\Delta\mu(z)|$, the energy storage in dz is $N_s[\Delta\mu(z)]^2dz$. The total energy storage is the sum of the following two terms

$$W_{sa}^F = \int_{-\infty}^0 N_s [\Delta\mu(z)]^2 dz, \quad (16)$$

$$W_{sa}^N = \int_0^{\infty} N_s [\Delta\mu(z)]^2 dz, \quad (17)$$

where W_{sa}^F and W_{sa}^N are the contributions from the FM and NM layers, respectively. Using (A.10) and (A.11), we can write them in a form resembling the energy stored in a capacitor

$$W_{sa}^F = \frac{1}{2} C_{sa}^F (V_c^F)^2, \quad W_{sa}^N = \frac{1}{2} C_{sa}^N (V_c^N)^2, \quad (18)$$

where (10) and (11) have also been used.

The energy stored in the SA capacitor is essentially the splitting energy of the spin-dependent chemical potentials instead of the electrostatic field energy associated with a geometrical capacitance. This character is similar to the quantum capacitance, which stores energy in the form of the Fermi degeneracy energy. [10] In general, quantum capacitance appears when the spatial charge accumulation on at least one plate of the capacitor induces a change in chemical potential. This is also true for the SA capacitance according to the discussion above. However, for the SA capacitance, the change in chemical potential happens in the spin degree of freedom instead of the coordinate space.

Leakage current Spin accumulation coexists with spin relaxation, in which electrons undergo transitions from the spin channel with higher chemical potential to the other via spin-flip scattering. This process can be modeled as the leakage of the SA capacitor (spin flux in [16]). If we set the positive direction of leakage current to be from the spin-down channel to the spin-up channel, the leakage current can be written as

$$J_{sf}^F = \int_{-\infty}^0 \frac{e N_s \mu_m(z)}{\tau_{sf}^F} dz, \quad (19)$$

$$J_{sf}^N = \int_0^{\infty} \frac{e N_s \mu_m(z)}{\tau_{sf}^N} dz, \quad (20)$$

for the FM and NM layers, respectively. Here $\tau_{sf} = 2T_1$ is the spin-flip scattering time. [17] Using (A.10) and (A.11), we can write J_{sf}^F and J_{sf}^N in a form resembling Ohm's law

$$J_{sf}^F = \frac{V_c^F}{r_F^{sf}} = \alpha_F \frac{J_0}{2}, \quad J_{sf}^N = \frac{V_c^N}{r_N^{sf}} = \alpha_N \frac{J_0}{2} \quad (21)$$

where (13) has been used. Therefore, r_F^{sf} and r_N^{sf} can be identified as the resistors in parallel with the SA capacitors as shown in figure 2(b). Using $\alpha_F + \alpha_N = \beta$, we have

$$\beta \frac{J_0}{2} = J_{sf}^F + J_{sf}^N, \quad (22)$$




Figure 2. (a) Sketch of the FM/NM junction with the spin-selective contact, which is signified by the thick vertical line at $z = 0$. The vertical dotted lines indicate the scale of spin diffusion lengths in the two layers. (b) An effective circuit of the spin transport (ECST) in the structure shown in sketch (a). The SA capacitors in figure 1 are connected in parallel with characteristic resistors in order to model the leakage due to spin relaxation. The resistances labeled by r_F^{sf} (r_N^{sf}) and r_F^{sd} (r_N^{sd}) have the same value $2r_F$ ($2r_N$). The superscripts “sf” and “sd” stand for spin flip and spin diffusion, respectively. The current densities J_{sf}^F , J_{sf}^N , and J_{sd}^C are given by (21) and (29), respectively. The current densities $\beta J_0/2$ and $\gamma J_0/2$ are generated by two current sources, the FM layer and the spin-selective contact, respectively.

which can also be derived directly by integrating (A.4) from $-\infty$ to ∞ . In fact, $\beta J_0/2$ is half of $J_m(-\infty)$, which is the spin current density produced by the bulk FM layer. This current decreases to zero exponentially at $z = \infty$ after the spin relaxation around the interface. During this process, half of $J_m(-\infty)$, that is $\beta J_0/2$, leaks from spin-down channel to spin-up channel in the FM and NM layers.

Heat generation Spin relaxation also generates heat as the spin-flip scattering causes decrease in the chemical potential of electrons. The heat generation rate due to spin-flip scattering can be written as

$$\Sigma_{\text{heat}}^{\text{F,sf}} = \int_{-\infty}^0 \frac{N_s [\mu_m(z)]^2}{\tau_{\text{sf}}^{\text{F}}} dz, \quad (23)$$

$$\Sigma_{\text{heat}}^{\text{N,sf}} = \int_0^{\infty} \frac{N_s [\mu_m(z)]^2}{\tau_{\text{sf}}^{\text{N}}} dz, \quad (24)$$

for the FM and NM layers, respectively. Using (A.10) and (A.11), we can write $\Sigma_{\text{heat}}^{\text{F,sf}}$ and $\Sigma_{\text{heat}}^{\text{N,sf}}$ formally as

$$\Sigma_{\text{heat}}^{\text{F,sf}} = r_{\text{F}}^{\text{sf}} (J_{\text{sf}}^{\text{F}})^2 = \frac{1}{2} r_{\text{F}} \alpha_{\text{F}}^2 J_0^2 \quad (25)$$

$$\Sigma_{\text{heat}}^{\text{N,sf}} = r_{\text{N}}^{\text{sf}} (J_{\text{sf}}^{\text{N}})^2 = \frac{1}{2} r_{\text{N}} \alpha_{\text{N}}^2 J_0^2 \quad (26)$$

where (21) has been used. Thus the heat generation can be modeled as the Joule heating of the resistors in parallel with the SA capacitors.

An effective circuit for spin transport We constructed an effective circuit, shown in figure 2(b), to model the spin transport, which takes place on the scale of the spin

diffusion lengths around the interface. There are two sources of the spin-polarized current in the junction: the FM layer with bulk spin asymmetry coefficient $\beta \neq 0$ and the contact with interfacial spin asymmetry coefficient $\gamma \neq 0$. They are represented by two independent current sources in the circuit: $\beta J_0/2$ and $\gamma J_0/2$. Both current sources drive current to flow from the spin-down to the spin-up channel in the NM layer. However, they drive opposite currents in the FM layer and the net current J_{sf}^{F} can be negative in some cases.

Two additional resistances, r_{F}^{sd} and r_{N}^{sd} , need to be introduced in the effective circuit to model the heat generation due to the spin diffusion in the FM and NM layers, denoted by $\Sigma_{\text{heat}}^{\text{F,sd}}$ and $\Sigma_{\text{heat}}^{\text{N,sd}}$, respectively. Using a macroscopic approach based on the Boltzmann equation, we can prove in general that the spin diffusion leads to the same heat generation as the spin relaxation (or the spin-flip scattering) in semi-infinite layers. [18] To meet this requirement, we connect r_{F}^{sd} and r_{N}^{sd} in series with r_{F}^{sf} and r_{N}^{sf} , respectively, as shown in figure 2(b). Then r_{F}^{sd} (r_{N}^{sd}) should be defined as $r_{\text{F}}^{\text{sd}} = r_{\text{F}}^{\text{sf}}$ ($r_{\text{N}}^{\text{sd}} = r_{\text{N}}^{\text{sf}}$) to satisfy $\Sigma_{\text{heat}}^{\text{F,sd}} = \Sigma_{\text{heat}}^{\text{F,sf}}$ and $\Sigma_{\text{heat}}^{\text{N,sd}} = \Sigma_{\text{heat}}^{\text{N,sf}}$. Using (25) and (26), we can write the spin-dependent heat generation as

$$\Sigma_{\text{heat}}^{\text{F}} = \Sigma_{\text{heat}}^{\text{F,sd}} + \Sigma_{\text{heat}}^{\text{F,sf}} = r_{\text{F}} \alpha_{\text{F}}^2 J_0^2, \quad (27)$$

$$\Sigma_{\text{heat}}^{\text{N}} = \Sigma_{\text{heat}}^{\text{N,sd}} + \Sigma_{\text{heat}}^{\text{N,sf}} = r_{\text{N}} \alpha_{\text{N}}^2 J_0^2, \quad (28)$$

for the FM and NM layers, respectively.

The currents J_{sf}^{F} and J_{sf}^{N} given by (21) can also be derived by applying the superposition theorem of electrical circuits to the circuit in figure 2(b). The effective potential drop on the resistance r_{F}^{sd} (r_{N}^{sd}) is also equal to that on r_{F}^{sf} (r_{N}^{sf}), which is consistent with (11). Moreover, using Kirchhoff's current law, one can calculate the current density flowing through the resistance $4r_{\text{b}}^*$

$$J_{\text{sd}}^{\text{C}} = J_{\text{sf}}^{\text{N}} - \gamma \frac{J_0}{2} = \alpha_{\text{C}} \frac{J_0}{2} \quad (29)$$

where we have introduced the dimensionless parameter

$$\alpha_{\text{C}} = \alpha_{\text{N}} - \gamma = \frac{\beta r_{\text{F}} - \gamma(r_{\text{F}} + r_{\text{N}})}{r_{\text{F}} + r_{\text{b}}^* + r_{\text{N}}}. \quad (30)$$

Then the effective potential drop on the resistance $4r_{\text{b}}^*$ can be written as $2(V_{\text{c}}^{\text{F}} - V_{\text{c}}^{\text{N}})$ or $[\mu_{\text{m}}(0^-) - \mu_{\text{m}}(0^+)]/e$. Using Joule's law, we can write the heat generation of the resistance $4r_{\text{b}}^*$ as

$$\Sigma_{\text{heat}}^{\text{C}} = 4r_{\text{b}}^* (J_{\text{sd}}^{\text{C}})^2 = \frac{(2V_{\text{c}}^{\text{F}} - 2V_{\text{c}}^{\text{N}})^2}{4r_{\text{b}}^*} = r_{\text{b}}^* \alpha_{\text{C}}^2 J_0^2, \quad (31)$$

which is equal to the result derived by using a more microscopic approach. [19] It has been shown, in [19], that $\Sigma_{\text{heat}}^{\text{C}}$ results only from the spin diffusion across the interface region (the spin relaxation at the interface is negligible [12]). Combining (27), (28), and (31), we can write the total heat generation due to the spin relaxation and diffusion as

$$\Sigma_{\text{heat}}^{\text{FN}} = \Sigma_{\text{heat}}^{\text{F}} + \Sigma_{\text{heat}}^{\text{N}} + \Sigma_{\text{heat}}^{\text{C}} = r_{\text{FN}}^* J_0^2, \quad (32)$$

where r_{FN}^* is defined as $r_{\text{FN}}^* = r_{\text{F}} \alpha_{\text{F}}^2 + r_{\text{N}} \alpha_{\text{N}}^2 + r_{\text{b}}^* \alpha_{\text{C}}^2$. One can verify that r_{FN}^* is equal to the spin-coupled interface resistance of the FM/NM junction. [12, 19]




Figure 3. (a) An equivalent circuit unit (ECU) for the ECST shown in figure 2(b). In the ECU, the current flowing through the various resistances is the total charge current J_0 , instead of the spin currents in ECST. The equivalent resistances r_F^* , r_N^* , and r_C^* are given in (33) and (34), respectively. The ESA capacitances $C_{sa}^{F,*}$ and $C_{sa}^{N,*}$ are defined in (37). (b) An overall equivalent circuit of the FM/NM junction shown in figure 2(a). The block labeled by “ECU” stands for the circuit unit in figure 3(a). The FM (NM) layer thickness t_F (t_N) is much larger than the spin diffusion length l_{sf}^F (l_{sf}^N).

An overall equivalent circuit In order to make the SA capacitance model comparable with Rashba’s theory and experimental results, we need construct an equivalent circuit for the ECST shown in figure 2(b). In the equivalent circuit, shown in figure 3, the current source is the total charge current J_0 instead of the spin current sources $\beta J_0/2$ and $\gamma J_0/2$. We require that the equivalent circuit has the same energy storage and heat generation as the ECST. We first determine the equivalent resistances by requiring the same heat generation. Using (27) and (28), we can set the equivalent resistances to be

$$r_F^* = r_F \alpha_F^2, \quad r_N^* = r_N \alpha_N^2, \quad (33)$$

for the FM and NM layers, respectively. Moreover, using (31), we can set the equivalent resistance for $4r_b^*$ in figure 2(b) to be

$$r_C^* = r_b^* \alpha_C^2, \quad (34)$$

which satisfies $r_{FN}^* = r_F^* + r_N^* + r_C^*$. Then the equivalent voltage drops on them can be written as

$$V_F^* = r_F^* J_0, \quad V_N^* = r_N^* J_0. \quad (35)$$

For simplicity, we assume that the equivalent spin-accumulation (ESA) capacitance $C_{sa}^{F,*}$ ($C_{sa}^{N,*}$) is connected in parallel with the whole r_F^* (r_N^*). Then, V_F^* (V_N^*) is also the voltage drop on $C_{sa}^{F,*}$ ($C_{sa}^{N,*}$). Finally, we require that $C_{sa}^{F,*}$ and $C_{sa}^{N,*}$ have the same energy storage as C_{sa}^F and C_{sa}^N

$$W_{sa}^F = \frac{1}{2} C_{sa}^{F,*} (V_F^*)^2, \quad W_{sa}^N = \frac{1}{2} C_{sa}^{N,*} (V_N^*)^2. \quad (36)$$

Substituting (18) and (35) into (36), we can find

$$C_{sa}^{F,*} = \frac{T_1^F}{2r_F^*} = \frac{C_{sa}^F}{\alpha_F^2}, \quad C_{sa}^{N,*} = \frac{T_1^N}{2r_N^*} = \frac{C_{sa}^N}{\alpha_N^2}, \quad (37)$$

for the FM and NM layers, respectively. An overall equivalent circuit is shown in figure 3(b), which also include the nominal resistances.

3. Reinterpretation of the magnetoimpedance

As an application of the SA or ESA capacitances, we will revisit the magnetoimpedance of the FM/NM junction by using the equivalent circuit shown in figure 3. The reactance in this configuration has been interpreted by Rashba in terms of the diffusion capacitance C_{diff} . [9]

The SA capacitance is approximately a constant for time-varying DC and (sinusoidal) AC signals in the regime for the quasi-static approximation to be valid. When the junction is driven by a constant DC current as discussed in the previous section, the spin accumulation is an exponential function in each layer and the SA capacitance is a constant independent on the current density. In general, the SA capacitance will change if the driving current becomes time-dependent, for example, a time-varying DC or AC signal. However, if the charge current $J(t)$ changes with time slowly enough that the solutions to the time-dependent equations are still exponential functions approximately at each moment, they can be replaced by the static solutions for the DC current of the same density $J(t)$. Then the SA capacitance can be assumed to be a constant for simplicity. This is the quasi-static approximation, which has been widely used in circuit analysis and also applied to the diffusion capacitance of a p-n junction. [1]

The valid range for the quasi-static approximation can be determined as follows. Since we are considering the impedance, it is enough to focus on the sinusoidal AC signal. The characteristic time scale of the spin dynamics is the spin relaxation time T_1^N , if we have the relation $T_1^N > T_1^F$ as usual. [13, 20] Therefore, the quasi-static approximation is valid if the frequency of the driving current satisfies $\omega \ll 1/T_1^N$ or equivalently $\omega C_{\text{sa}}^{N,*} \ll 1/(2r_N^*)$. In practice, most experiments on time-dependent transport use slowly-varying or low-frequency AC signals. [2, 4] In the high-frequency regime, the quasi-static approximation breaks down because the spin dynamics cannot follow the variation of the driving signal and the spin accumulation deviates from the exponential form severely. [13] In this case, the spin wave-diffusion theory should be used instead. Consequently, the inductive terms becomes remarkable and may be dominant over the capacitive terms if the frequency is high enough. [21]

If the AC current density is set to be $J(t) = J_0 \exp(-i\omega t)$, the impedances of $C_{\text{sa}}^{F,*}$ and $C_{\text{sa}}^{N,*}$ in figure 3(a) can be written, respectively, as $i/(\omega C_{\text{sa}}^{F,*})$ and $i/(\omega C_{\text{sa}}^{N,*})$ using the quasi-static approximation. Using usual circuit theorems, we can calculate the impedance, Z_{ECU} , of the ECU in figure 3(a). Then expanding Z_{ECU} in terms of ω and keeping up to the first-order terms, we have

$$Z_{\text{ECU}} = r_{\text{FN}}^* + iX_{\text{sa}}^{\text{FN}}, \quad (38)$$

where r_{FN}^* is defined in (32) and the reactance $X_{\text{sa}}^{\text{FN}}$ can be written as

$$X_{\text{sa}}^{\text{FN}} = \omega C_{\text{sa}}^{F,*} (r_{\text{F}}^*)^2 + \omega C_{\text{sa}}^{N,*} (r_{\text{N}}^*)^2. \quad (39)$$

Next we will prove that the impedance given in (38) is equal to that derived by Rashba ($Z_{\text{n-eq}}$) in the low-frequency regime. [9] Rashba's basic results are outlined with our notations in Appendix C. Using (14) and (30) in the present paper, we can rewrite the real part of the impedance, $R_{\text{n-eq}}$ given in (C.3), in a form with more transparent physical interpretation

$$R_{\text{n-eq}} = r_{\text{F}}^* + r_{\text{N}}^* + r_{\text{C}}^* = r_{\text{FN}}^*, \quad (40)$$

which is equal to the real part of Z_{ECU} in (38). The imaginary part of the impedance, $\text{Im}(\mathcal{Z}_{\text{n-eq}})$ given in (C.4), can be rewritten as

$$\text{Im}(\mathcal{Z}_{\text{n-eq}}) = \omega \frac{T_1^{\text{F}}}{2r_{\text{F}}} (r_{\text{F}}\alpha_{\text{F}})^2 + \omega \frac{T_1^{\text{N}}}{2r_{\text{N}}} (r_{\text{N}}\alpha_{\text{N}})^2, \quad (41)$$

where we have used (14) and (30). Then using the SA capacitances defined in (10), we can write (41) as

$$\text{Im}(\mathcal{Z}_{\text{n-eq}}) = \omega C_{\text{sa}}^{\text{F}} (r_{\text{F}}\alpha_{\text{F}})^2 + \omega C_{\text{sa}}^{\text{N}} (r_{\text{N}}\alpha_{\text{N}})^2. \quad (42)$$

Finally, by using (33) and (37), we can prove that $\text{Im}(\mathcal{Z}_{\text{n-eq}})$ is equal to $X_{\text{sa}}^{\text{FN}}$ in (39). Therefore, the impedance Z_{ECU} is the same as $\mathcal{Z}_{\text{n-eq}}$ derived by Rashba and the ECU shown in figure 3(a) can also be used to interpret $\mathcal{Z}_{\text{n-eq}}$.

In comparison to Rashba's theory, we wrote the reactance of the FM/NM junction in terms of the SA or ESA capacitances instead of the diffusion capacitance C_{diff} defined in (C.5). One benefit is that the form of the SA or ESA capacitances resemble obviously that of the diffusion capacitance in a p-n junction. More importantly, our results revealed the form of the energy storage associated with the reactance. In the low-frequency limit, the energy storage associated with $\mathcal{Z}_{\text{n-eq}}$ is given by (18) or (36), which is the splitting energy of the spin-dependent chemical potentials instead of the electrostatic energy. Our results also suggest a way to calculate the reactance without using the time-dependent equations.

One characteristic of the reactance, $X_{\text{sa}}^{\text{FN}}$, is that it is zero if $\beta = 0$ and $\gamma = 0$. This means that a spin-current source is indispensable to the reactance we consider. Multilayers with $\beta = 0$ and $\gamma = 0$ may still have parasitic capacitance in parallel with resistance as long as the material resistivity varies from layer to layer. It results from the induced charge accumulation at the interfaces, which adjusts the electric field in different layers to maintain a homogeneous current across the entire multilayer. The energy stored in this kind of capacitance is essentially electrostatic energy and it will not be discussed in this paper.

4. Conclusions

In a metal or degenerate semiconductor, the two spin channels can be modeled as the two plates of a capacitor. The spin-accumulation capacitance can be introduced to measure the ability of the material to store spins instead of charge. The energy stored in the SA capacitor is the splitting energy of the spin-dependent chemical potentials instead of the electrostatic energy. The leakage of the SA capacitor models the spin relaxation. The heat generation due to the spin relaxation can be written formally as the Joule heating of the resistance in parallel with the SA capacitor. Equivalent circuits can be constructed to give a transparent interpretation of the model for a typical FM/NM junction.

As an application of the model, we derived the magnetoimpedance of the FM/NM junction directly from the equivalent circuit using the quasi-static approximation. We rewrote the reactance in terms of the SA capacitances, whose formula is obviously similar to that of the diffusion capacitance in a p-n junction. Our results also revealed the form of energy storage associated with the reactance. We expect that the SA capacitance can be generalized to other structures, such as MTJs, and used to interpret the ongoing experiments on the magnetoimpedance.

5. Acknowledgments

We thank Prof. H. C. Schneider and Y. Suzuki for fruitful discussions. This work was supported by National Natural Science Foundation of China (grant numbers 11404013, 11605003, 61405003, 11474012).

Appendix A. The FM/NM junction driven by a constant DC

According to the Valet-Fert theory, [12] $\Delta\mu(z)$ and current density $J_{\pm}(z)$ satisfy the following equations

$$\frac{e}{\sigma_{\pm}} \frac{\partial J_{\pm}}{\partial z} = \pm 2 \frac{\Delta\mu}{l_{\pm}^2}, \quad (\text{A.1})$$

$$J_{\pm} = \sigma_{\pm} \left(F \pm \frac{1}{e} \frac{\partial \Delta\mu}{\partial z} \right), \quad (\text{A.2})$$

where $\sigma_{\pm}$ and $l_{\pm}$ denote the conductivity and spin-diffusion length for spin “ $\pm$ ” (“up” or “down”), respectively. In FM layers, the conductivity $\sigma_{\pm}$ satisfies the relation $1/\sigma_{\uparrow(\downarrow)} = 2\rho_F^*[1-(+)\beta]$, where the subscript “ $\uparrow$ ” (“ $\downarrow$ ”) denotes the majority (minority) spin direction. Similarly, we have $1/\sigma_{\uparrow(\downarrow)} = 2\rho_N^*$ in NM layers. The field F is defined as $F = (1/e)\partial\bar{\mu}/\partial z$ and $\bar{\mu} = (\bar{\mu}_+ + \bar{\mu}_-)/2$ is the average electrochemical potential.

Several important equations can be derived from (A.1) and (A.2). Subtracting the “ $\pm$ ” components of (A.1) directly, we have

$$\frac{\partial J_m}{\partial z} = \frac{\Delta\mu}{er_{F(N)}l_{sf}^{F(N)}}, \quad (\text{A.3})$$

where we have introduced the spin current density $J_m(z) = J_+(z) - J_-(z)$. The spin diffusion length is defined by $1/l_{sf}^2 = 1/l_+^2 + 1/l_-^2$. The resistance r_F (r_N) is defined in (12). Multiplying $\sigma_{\pm}$ on both sides of (A.1) and subtracting its “ $\pm$ ” components, we have

$$\frac{\partial J_m}{\partial z} = \frac{4eN_s\Delta\mu}{\tau_{sf}^{F(N)}}, \quad (\text{A.4})$$

where $\sigma_{\pm} = e^2N_sD_{\pm}$ and $l_{\pm}^2 = D_{\pm}\tau_{sf}$ have been used. [13] Moreover, $D_{\pm}$ is the diffusion constant for spin “ $\pm$ ”. Comparing (A.3) and (A.4), we can find the relation

$$\frac{T_1^{F(N)}}{2r_{F(N)}} = e^2N_sl_{sf}^{F(N)}, \quad (\text{A.5})$$

where $\tau_{sf}^{F(N)} = 2T_1^{F(N)}$ has been used. Dividing both sides of (A.2) by $\sigma_{\pm}$ and then subtracting its “ $\pm$ ” components, we have

$$J_m = \mp\beta J + \frac{1}{e\rho_F^*} \frac{\partial \Delta\mu}{\partial z} \quad (\text{A.6})$$

for FM layers. Here, “ $-$ ” (“ $+$ ”) corresponds to “up” (“down”) magnetization of the FM layer. For NM layers, one only needs to set $\beta = 0$ and replace ρ_F^* by ρ_N^* in (A.6). Substituting (A.6) into (A.3), we can derive (2) in section 2.

At the interface located at $z = 0$, the electrochemical potential $\bar{\mu}_{\pm}(z)$ and $J_{\pm}(z)$ satisfy the boundary conditions

$$J_s(0^+) - J_s(0^-) = 0, \quad (\text{A.7})$$

$$\bar{\mu}_s(0^+) - \bar{\mu}_s(0^-) = er_s J_s(0), \quad (\text{A.8})$$

where the interface resistance r_s can be written as

$$r_{\uparrow(\downarrow)} = 2r_b^* [1 - (+) \gamma]. \quad (\text{A.9})$$

Here, γ is the interfacial spin asymmetry coefficient and $\uparrow$ ($\downarrow$) denotes the majority (minority) spin channel.

Applying the Valet-Fert theory to the FM/NM junction considered in section 2, we have

$$\Delta\mu(z) = \Delta\mu(0^-) \exp(z/l_{\text{sf}}^{\text{F}}), \quad z < 0 \quad (\text{A.10})$$

$$\Delta\mu(z) = \Delta\mu(0^+) \exp(-z/l_{\text{sf}}^{\text{N}}), \quad z > 0 \quad (\text{A.11})$$

where we have introduced

$$\Delta\mu(0^-) = er_{\text{F}}\alpha_{\text{F}}J_0, \quad \Delta\mu(0^+) = er_{\text{N}}\alpha_{\text{N}}J_0. \quad (\text{A.12})$$

The parameters α_{F} and α_{N} are defined in (14).

Substituting (A.10) into (7), we can write Q_{sa}^{F} as

$$Q_{\text{sa}}^{\text{F}} = e^2 N_{\text{s}} l_{\text{sf}}^{\text{F}} V_{\text{c}}^{\text{F}} \quad (\text{A.13})$$

where V_{c}^{F} is defined in (11). Substituting (A.5) into (A.13), we find

$$Q_{\text{sa}}^{\text{F}} = C_{\text{sa}}^{\text{F}} V_{\text{c}}^{\text{F}} \quad (\text{A.14})$$

where $C_{\text{sa}}^{\text{F}} = T_{\text{I}}^{\text{F}}/(2r_{\text{F}})$ is the same as that defined in (10). One can also rewrite Q_{sa}^{N} in a similar way.

Appendix B. Quasi-neutrality approximation

The average chemical potential $\mu(z)$ can be simplified by using the quasi-neutrality approximation. The nonequilibrium charge density of each spin channel, $\rho_{\pm}(z)$, has two exponential terms with different decaying lengths: the Thomas-Fermi screening length and the spin diffusion length. [14] The two terms will be discussed separately in the following.

The screening length is on the order of angstrom and the charge accumulation of this length scale is not spin-polarized. Therefore, the screening charge can be considered as an interfacial charge layer, which gives rise to a constant electric field on each side of the interface. It leads to a parasitic capacitance that is beyond the scope of the present paper and thus the screening charge becomes irrelevant to our problem.

On the scale of the spin diffusion length, one spin channel has an excess of electrons while the other is deficient in electrons. The excess and deficiency cancel each other exactly in the NM layer, but they are slightly different in magnitude in the FM layer, which results in a net charge accumulation coexisting with the spin accumulation. The ratio of the net electron concentration to the excess of electrons in one spin channel (or deficiency in the other) satisfies $\beta\lambda_{\text{TF}}^2/[(l_{\text{sf}}^{\text{F}})^2 - \lambda_{\text{TF}}^2] \ll 1$ for typical ferromagnetic metals. This net charge accumulation can be neglected for some problems, such as the SA capacitance, in which only the spin-dependent charge densities and the associated chemical potentials really matter. On the other hand, this net charge accumulation also leads to an exponentially-decaying electric field, which in turn results in an extra electric potential. It has been proven that the electric potential energy is much larger than the chemical potential at a certain position and dominates the electrochemical potential. [14] Therefore, the net charge accumulation is necessary for some problems, such as the interpretation of the GMR effects, where the extra potential drop plays a crucial role. [12] This interpretation is essentially the widely-used quasi-neutrality approximation.

Appendix C. Rashba's results for the magnetoimpedance

According to (12) and (13) of Rashba's paper, [9] the nonequilibrium impedance of the FM/NM junction can be rewritten as

$$\mathcal{Z}_{\text{n-eq}}(\omega) = \frac{1}{r_{\text{FN}}(\omega)} \left[r_{\text{N}}(\omega) r_{\text{b}}^* \gamma^2 + r_{\text{N}}(\omega) r_{\text{F}}(\omega) \beta^2 + r_{\text{b}}^* r_{\text{F}}(\omega) (\gamma - \beta)^2 \right] \quad (\text{C.1})$$

where $r_{\text{FN}}(\omega)$ is defined as $r_{\text{FN}}(\omega) = r_{\text{F}}(\omega) + r_{\text{N}}(\omega) + r_{\text{b}}^*$. To simplify the expression, we have substituted γ and β for $\Delta\Sigma/\Sigma$ and $\Delta\sigma/\sigma_{\text{F}}$ (used by Rashba [9]), respectively. The resistance r_{b}^* is the same as r_{c} in [9]. The frequency-dependent $r_{\text{F(N)}}(\omega)$ is defined as

$$r_{\text{F}}(\omega) = \frac{r_{\text{F}}}{\sqrt{1 - i\omega T_{\text{F}}^{\text{F}}}}, \quad r_{\text{N}}(\omega) = \frac{r_{\text{N}}}{\sqrt{1 - i\omega T_{\text{F}}^{\text{N}}}} \quad (\text{C.2})$$

where T_{F}^{F} (T_{F}^{N}) is the same as τ_s^{F} (τ_s^{N}) in [9]. Expanding $\mathcal{Z}_{\text{n-eq}}(\omega)$ in ω and keeping up to the first-order terms, one can write its real part as

$$R_{\text{n-eq}} = \frac{r_{\text{N}} r_{\text{b}}^* \gamma^2 + r_{\text{N}} r_{\text{F}} \beta^2 + r_{\text{b}}^* r_{\text{F}} (\gamma - \beta)^2}{r_{\text{FN}}} \quad (\text{C.3})$$

which is just (10) of Rashba's paper. [9] The imaginary part in the expansion of $\mathcal{Z}_{\text{n-eq}}(\omega)$ can be written as

$$\text{Im}(\mathcal{Z}_{\text{n-eq}}) = \omega R^2 C_{\text{diff}} \quad (\text{C.4})$$

where the diffusion capacitance is defined as

$$C_{\text{diff}} = \frac{1}{2R^2 r_{\text{FN}}^2} \left\{ T_{\text{F}}^{\text{N}} r_{\text{N}} (\gamma r_{\text{b}}^* + \beta r_{\text{F}})^2 + T_{\text{F}}^{\text{F}} r_{\text{F}} [\gamma r_{\text{b}}^* - \beta (r_{\text{b}}^* + r_{\text{N}})]^2 \right\} \quad (\text{C.5})$$

and R defined as $R = R_{\text{n-eq}} + (1 - \gamma^2) r_{\text{b}}^*$.

References

- [1] Neamen D A 2012 *Semiconductor Physics and Devices: Basic Principles* 4th ed (New York: McGraw-Hill)
- [2] Landry G, Dong Y, Du J, Xiang X and Xiao J Q 2001 *Appl. Phys. Lett.* **78** 501
- [3] Chui S T and Hu L 2002 *Appl. Phys. Lett.* **80** 273
- [4] Chien W C, Lo C K, Hsieh L C, Yao Y D, Han X F, Zeng Z M, Peng T Y and Lin P 2006 *Appl. Phys. Lett.* **89** 202515
- [5] Padhan P, LeClair P, Gupta A, Tsunekawa K and Djayaprawira D D 2007 *Appl. Phys. Lett.* **90** 142105
- [6] Kaiju H, Takei M, Misawa T, Nagahama T, Nishii J and Xiao G 2015 *Appl. Phys. Lett.* **107** 132405
- [7] Parui S, Ribeiro M, Atxabal A, Bedoya-Pinto A, Sun X, Llopis R, Casanova F and Hueso L E 2016 *Appl. Phys. Lett.* **109** 052401
- [8] Lee T H and Chen C D 2015 *Sci. Rep.* **5** 13704
- [9] Rashba E I 2002 *Appl. Phys. Lett.* **80** 2329
- [10] Luryi S 1988 *Appl. Phys. Lett.* **52**(6) 501
- [11] Datta S 2005 *Quantum transport: atom to transistor* (Cambridge, UK: Cambridge University Press)
- [12] Valet T and Fert A 1993 *Phys. Rev. B* **48** 7099
- [13] Zhu Y H, Hillebrands B and Schneider H C 2008 *Phys. Rev. B* **78** 054429
- [14] Zhu Y H, Xu D H and Geng A C 2014 *Physica B* **446** 43
- [15] Fert A and Jaffrès H 2001 *Phys. Rev. B* **64**(18) 184420

- [16] Wegrowe J E and Drouhin H J 2011 *Entropy* **13** 316–331
- [17] Fert A and Lee S F 1996 *Phys. Rev. B* **53**(10) 6554–6565
- [18] Zhang X X, Zhu Y H, He P S and Li B H 2017 Mechanisms of spin-dependent heat generation in spin valves arXiv: 1702.05286
- [19] Zhang X X, Zhu Y H, He P S and Li B H 2017 An alternative to the spin-coupled interface resistance for describing heat generation arXiv: 1702.05283
- [20] Zhang S and Levy P M 2002 *Phys. Rev. B* **65** 052409
- [21] Zhu Y H and Schneider H C 2009 *IEEE Trans. Magn.* **45** 3495